

Da Vinci Smart Manufacturing

BRD S04.01.02 Master Data Material **Maintenance ByProducts**

Version	Created/Modified by	Description	Date
1.0	Sahana Badal	S04.01.02 First Draft	14/07/2025

1. By Prodcuts List Screen.....	3
2. Add Material Details.....	7
Material Information Tab.....	7
Material Specification Tab.....	9
3. Edit Material Details.....	11
Material Information Tab.....	12
Material Specification Tab.....	13
4. View Material	16
Material Information Tab.....	16
Material Specification Tab.....	18

1. By Prodcuts List Screen

This is designed to provide a comprehensive and user-friendly interface for managing By Prodcuts, including both active and inactive materials. **This data is populated from an external system and are loaded initially in inactive state.** Users can filter, search, and sort materials based on various parameters like Material Type and Material Status.

Header Section

- **Title:** "MM : By Prodcuts"
- **Stats Section:** Total count of Active | Inactive
- **Search Bar:** Tooltip text: Search by Material ID / Material Name
- **Filters:**
 - Material Type -
 - Multi-select Dropdown
 - All Material Types related to By Prodcuts
 - Status -
 - Multiselect Dropdown:
 - Values: Active | Inactive
 - Clear Filter - This will clear all the applied filters
 - All Filter drop downs should be sorted alphabetically / numerically

Material List Section

Users can view the list of all By Prodcuts, including both active and inactive materials. This data is populated from an external system and are loaded initially in inactive state. Users can filter, search, and sort materials based on various parameters like Material Type and Material Status. The table will have the following columns:

Table Default Sorting : Latest Modified first

- ☐ **Material ID:**
 - **Material ID**
 - Sorting: Yes
 - Frozen - Yes
- ☐ **Material Name:**
 - **Material Name corresponding to the Material ID**
 - Sorting: Yes
 - Frozen: No
- ☐ **Material Type:**
 - Material Type, the material ID belongs to
 - Sorting: Yes
 - Frozen: No
- ☐ **Created At:**
 - **Date Material was created as per ERP system**
 - Sorting: Yes

- Frozen: No
- **Created By**
 - Auto-populated as “System“
 - Sorting: Yes
 - Frozen: No
- **Modified At**
 - Last record modified Date and time
 - Sorting: Yes
 - Frozen – No
- **Modified By**
 - User ID | First Name Last Name of user who last modified the record
 - Sorting: Yes
 - Frozen – No
- **Status:** Indicates the status of the record (Draft, New, Linked, Rejected).
 - **Active** –Material that are activated in the system.
 - **Inactive** – Material imported from the ERP are initially marked as inactive or have been deactivated within the system.
 - Sorting: Yes
 - Frozen: No

Note: Horizontal scroll is required to be able to navigate through all columns and visualize all data but always respecting the frozen columns.

- **Action Buttons:** Depending on the status, allows users to edit or view the record. Only users with Create/Edit permissions on the module can activate, edit, or deactivate materials.
 - **Active:**
 - View – Record details can be viewed in non-editable mode
 - Edit - Details can be edited in the Material Information and Specification tab.
 - Deactivate - Users can deactivate an active material, which moves it to an inactive state. Deactivate the material after a confirmation message
 - “Do you want to deactivate this material “MAT ID”?”
 - **Inactive: Material Information tab details have not been saved**
 - View – Record details can be viewed in non-editable mode
 - Add Details – Additional details can be included in the Material Information and Specification tab.
 - **Inactive: Material Information tab details have been saved**
 - View – Record details can be viewed in non-editable mode
 - Edit - Details can be edited in the Material Information and Specification tab.
 - Activate - Users with the appropriate permissions can activate an inactive material by adding additional information and specifying the material’s elemental specifications. Activate the material after a confirmation message
 - “Do you want to activate this material “MAT ID”?”

- **Pagination Controls:** Navigation buttons to browse through multiple pages of records, if applicable (for more than 10 records).
- Rows Per page : Default 10, Dropdown values: 10, 20, 30, 40, 50

Export Function: The export function must extract ALL the information of the columns available on list screen even they are not displayed.

Material ID	Material Name	Material Type	Created At	Created By	Modified At	Modified By	Status
D030_24	Bec 0/25	By Prodcuts	04/06/2025 06:27 AM	Sahana Sahana Badal			Active
D030_103	Ferreux	By Prodcuts	04/06/2025 06:27 AM	Sahana Sahana Badal	04/06/2025 06:27 AM	Sahana Sahana Badal	Active
D030_108	Bec 0/25	By Prodcuts	04/06/2025 06:27 AM	Sahana Sahana Badal	04/06/2025 06:27 AM	Sahana Sahana Badal	Inactive
D030_23	Bec 0/25	By Prodcuts	04/06/2025 06:27 AM	Sahana Sahana Badal	04/06/2025 06:27 AM	Sahana Sahana Badal	Active
XXXX_186	Cible Haut Alu	By Prodcuts	04/06/2025 06:27 AM	Sahana Sahana Badal			Inactive
XXXX_198	Cible DopE P	By Prodcuts	04/06/2025 06:27 AM	Sahana Sahana Badal	04/06/2025 06:27 AM		Inactive

D030_2	Si 0/18 recoulEe	By Prodcuts	04/06/2025 06:27 AM	Sahana Sahana Badal			Inactiv e
--------	------------------	-------------	-----------------------	-----------------------	--	--	--------------

Exported File Name: “ByProdcuts_DDMMYY”

Customize Columns: Users can enable or disable all columns based on their preference. Only the enabled columns will be visible in the list. Columns marked as ‘frozen’ will be enabled by default and cannot be modified.

MM: By Products Active 5 Inactive 35

Q Search Filters Export

Material ID	Material Name	Material Type	Created At	Status
C910_9	SIO2DM	Silica Fume	10/10/2024	Active
C910_7	SIO2MWDM	Silica Fume	10/10/2024	Active
DSF1_204	PS Silicium brut 2.5 / 5	Silica Fume	10/10/2024	Active
C910_272	SIO2DP FIBRE CEMENT	Silica Fume	10/10/2024	Active
DSF1_161	PS SILICIUM 1.2 / 2.5	Silica Fume	10/10/2024	Active
C910_8	SIO2MR	Silica Fume	10/10/2024	Inactive
D046_279	HF Interne	Silica Fume	10/10/2024	Active
C910_271	SIO2DP PRENIUM	Silica Fume	10/10/2024	Active
C910_214	SIO2-DP	Silica Fume	10/10/2024	Inactive
C910_273	SIO2 DM PRENIUM	Silica Fume	10/10/2024	Active

Showing 10 of 80 < 1 2 3 ... 8 > Rows Per Page: 10

The screenshot shows a web application interface for managing materials. The main header is 'MM: By Products' with sub-headers 'Active 5' and 'Inactive 35'. Below this is a search bar and a 'Filters' button. The table displays columns for Material ID, Material Name, Material Type, Created At, and Status. The sidebar on the right contains 'FILTERS' with a 'Clear' button and two dropdown menus for 'Material Type' and 'Status'.

Material ID	Material Name	Material Type	Created At	Status
C910_9	SIO2DM	Silica Fume	10/10/2024	Act
C910_7	SIO2MWDM	Silica Fume	10/10/2024	Act
DSF1_204	PS Silicium brut 2.5 / 5	Silica Fume	10/10/2024	Act
C910_272	SIO2DP FIBRE CEMENT	Silica Fume	10/10/2024	Act
DSF1_161	PS SILICIUM 12 / 2.5	Silica Fume	10/10/2024	Act
C910_8	SIO2MR	Silica Fume	10/10/2024	Inac
D046_279	HF Interne	Silica Fume	10/10/2024	Act
C910_271	SIO2DP PREMIUM	Silica Fume	10/10/2024	Act
C910_214	SIO2-DP	Silica Fume	10/10/2024	Inac
C910_273	SIO2 DM PREMIUM	Silica Fume	10/10/2024	Act

Showing 10 of 80

2. Add Material Details

This screen will allow users to input and manage records, organised into two Tabs: Material Information and Material Specification. Mandatory fields will be marked with an asterisk (*). Below is a detailed layout incorporating the requirements.

Header: Back Icon | **C910_8** | **SIO2MR** (Material ID | Material Name)

Material Information Tab

Basic Information (Read-only; fetched from external ERP system):

- Material ID = (Concatenation of ERP ID and Ops ID)
- Material Name
- ERP Commercial Material ID
- ERP Commercial Material Name
- ERP ACC Material ID
- ERP ACC Material Name
- Ops Technical Material ID
- Material Type
- Status
- Date Created
- Material Description

Additional Information - These details are to be captured here, they are the following

- **Effective Date*:**
 - User selects the date from a calendar selector. The system shall allow users to capture a set of values with an effective date, which can be in the past, present, or future.
 - Mandatory - Yes

- Default value - Current date
- Field Type - Calendar picker
- Validation - No
- **Unit Weight***
 - User inputs the unit weight value
 - Mandatory - Yes
 - Default value - None
 - Field Type - User input
 - Validation - Numeric 2 decimal values. Max allowed 99,999,999.99
 - Units - Kg
- **Density**
 - User inputs the value
 - Mandatory - No
 - Default value - None
 - Field Type - User input
 - Validation - Numeric 4 decimal values. Max allowed 99,999,999.9999
 - Units - Depending on Unit System setup on Plant config (g/l metric system or lbm/ft^3)

Action Buttons

- **Save & Continue:**
 - Upon saving the details, the user is redirected to the **Material Specification** tab.
 - On the **list screen**:
 - Since the first tab's details have been entered,
 - An **Edit** option will appear in the **action menu** for the corresponding item.
 - Since Material Specification has default 0 values, User can now activate the material.
- **Cancel:** Cancels the current operation and returns to the list screen

Material ID	Material Name	ERP Commercial Material ID	ERP Commercial Material Name	ERP ACC Material ID
C910_9	SIO2DM	C9DM	MICROFUMEE CONCRETE DM	C910

ERP ACC Material Name: FumEe de silice
Ops Technical Material ID: 9
Material Type: Silica Fume
Status: Active
Date Created: 01/21/2025

Material Description: FUMEE DE SILICE DENSIFIEE MECANIQUE

Additional Information

Effective Date*: 18.08.24

Unit Weight*: Enter Value t
Density*: Enter Value g/cm³

Cancel Save & Continue

Material Specification Tab

- The Material Specification tab is not dependent on the completion or saving of the Material Information tab.
- Users can navigate to and save data under the Material Specification tab without saving the Material Information tab.
- The material cannot be activated unless all mandatory fields in the Material Information tab are filled in and saved successfully.
- Users can edit material specifications, including chemistry, physical and size specifications.
- Under this section “Low”, “Aim” and “High” values for various elements are captured. The elements are mapped to a particular material type.
- In Edit mode update of element values inserts a new set of records with the date.
- For any given date only one set can exist, the older values will be overwritten for an existing date. Thus, storing historical data will help generate reports with appropriate data for all dates.
- Historical data can be viewed by downloading the Excel file using the download option in View mode
- The list of elements for Chemical and Physical can be seen in the design provided.
- Material Specification tab is independent from Material Information tab and available to be saved at any point of time.
- **Each Chemistry element will have the following :** Fe, Si, C, Mn, Cr, Ni, Mo, V, Ti, Al, W, Nb, Co, Zr, B, P, S, Cu, Sn, Pb, Mg, Ca, Zn, As, Sb, Se, Te, Re, Ta, Hf, Sc, Y, La, Ce, Nd, Pr, Sm, Gd, Dy, Er, Be, Li, Na, K, Sr, Ga, Ge, Cd, In, Hg, Pt, Au
 - Low -
 - Editable and pre-populated with default value.
 - Default value - 0
 - Mandatory: No
 - Field Validation -
 - only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be lower than Aim and High
 - Aim
 - Editable and pre-populated with default value.
 - Default value - 0
 - Mandatory: No
 - Field Validation -
 - only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be higher than Low and lower than High
 - High
 - Editable and pre-populated with default value.
 - Default value - 0
 - Mandatory: No
 - Field Validation -

- only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be higher than Low and Aim
- **Each Physical element will have the following:** Ash, Moisture, Volatiles.
 - Low -
 - Editable and pre-populated with default value.
 - Mandatory - No
 - Default - 0
 - Field Validation -
 - only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be lower than Aim and High
 - Aim
 - Editable and pre-populated with default value.
 - Mandatory - No
 - Default - 0
 - Field Validation -
 - only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be higher than Low and lower than High
 - High
 - Editable and pre-populated with default value.
 - Mandatory - No
 - Default - 0
 - Field Validation -
 - only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be higher than Low and Aim
- **Action Buttons**
 - **Save**
 - Upon saving the details, the user is redirected to the **List** page.
 - On the **list screen**:
 - Since both tab's details have been entered,
 - An **Edit** option will appear in the **action menu** for the corresponding item.
 - User can now activate the material
 - **Cancel**: Cancels the current operation and returns to the list screen

C910_9 | SIO2DM

Nora James

Material Information

Material Specification

Chemistry Elements

Elements (in %)	Low	Aim	High
Al	0.0000	0.0000	0.0000
As	0.0000	0.0000	0.0000
Au	0.0000	0.0000	0.0000
B	0.0000	0.0000	0.0000
Be	0.0000	0.0000	0.0000
C	0.0000	0.0000	0.0000
Ca	0.0000	0.0000	0.0000
Cd	0.0000	0.0000	0.0000
Ce	0.0000	0.0000	0.0000
Cu	0.0000	0.0000	0.0000

Elements (in %)	Low	Aim	High
Hf	0.0000	0.0000	0.0000
Hg	0.0000	0.0000	0.0000
In	0.0000	0.0000	0.0000
K	0.0000	0.0000	0.0000
La	0.0000	0.0000	0.0000
Li	0.0000	0.0000	0.0000
Mg	0.0000	0.0000	0.0000
Mn	0.0000	0.0000	0.0000
Mo	0.0000	0.0000	0.0000
Nb	0.0000	0.0000	0.0000

Elements (in %)	Low	Aim	High
Sb	0.0000	0.0000	0.0000
Sc	0.0000	0.0000	0.0000
Se	0.0000	0.0000	0.0000
Si	0.0000	0.0000	0.0000
Sm	0.0000	0.0000	0.0000
Sn	0.0000	0.0000	0.0000
Sr	0.0000	0.0000	0.0000
S	0.0000	0.0000	0.0000
Ta	0.0000	0.0000	0.0000
Tb	0.0000	0.0000	0.0000

Cancel Save

C910_9 | SIO2DM

Elements (in %)	Low	Aim	High
V	0.0000	0.0000	0.0000
Cu	0.0000	0.0000	0.0000
C	0.0000	0.0000	0.0000
Dy	0.0000	0.0000	0.0000
Er	0.0000	0.0000	0.0000
Fe	0.0000	0.0000	0.0000
Ga	0.0000	0.0000	0.0000
Gd	0.0000	0.0000	0.0000

Elements (in %)	Low	Aim	High
Hf	0.0000	0.0000	0.0000
Nd	0.0000	0.0000	0.0000
Ni	0.0000	0.0000	0.0000
P	0.0000	0.0000	0.0000
Pb	0.0000	0.0000	0.0000
Pr	0.0000	0.0000	0.0000
Pt	0.0000	0.0000	0.0000
P	0.0000	0.0000	0.0000

Elements (in %)	Low	Aim	High
V	0.0000	0.0000	0.0000
V	0.0000	0.0000	0.0000
W	0.0000	0.0000	0.0000
Y	0.0000	0.0000	0.0000
Zn	0.0000	0.0000	0.0000
Zr	0.0000	0.0000	0.0000

Physical Elements

Elements (in %)	Low	Aim	High
Ash	0.0000	0.0000	0.0000

Elements (in %)	Low	Aim	High
Moisture	0.0000	0.0000	0.0000

Elements (in %)	Low	Aim	High
Volatiles	0.0000	0.0000	0.0000

Cancel Save

3. Edit Material Details

- This screen will allow users to input and manage records, organized into two Tabs: Material Information and Material Specification. Mandatory fields will be marked with an asterisk (*). Below is a detailed layout incorporating the requirements.
- **Header:** Back Icon | **C910_8 | SIO2MR** (Material ID | Material Name)

MM: By Products Active 5 Inactive 35

Q Search Filters Export

Material ID	Material Name	Material Type	Created At	Status	
C910_9	SIO2DM	Silica Fume	10/10/2024	Active	
C910_7	SIO2MWDMM	Silica Fume	10/10/2024	Active	
DSF1_204	PS Silicium brut 2.5 / 5	Silica Fume	10/10/2024	Active	
C910_272	SIO2DP FIBRE CEMENT	Silica Fume	10/10/2024	Active	
DSF1_161	PS SILICIUM 1.2 / 2.5	Silica Fume	10/10/2024	Active	
C910_8	SIO2MR	Silica Fume	10/10/2024	Inactive	
DO46_279	HF Interne	Silica Fume	10/10/2024	Active	
C910_271	SIO2DP PREMIUM	Silica Fume	10/10/2024	Active	
C910_214	SIO2-DP	Silica Fume	10/10/2024	Inactive	
C910_273	SIO2 DM PREMIUM	Silica Fume	10/10/2024	Active	

Showing 10 of 80 < 1 2 3 ... 8 > Rows Per Page: 10

Material Information Tab

Basic Information (Read-only; fetched from external ERP system):

- Material ID = (Concatenation of ERP ID and Ops ID)
- Material Name
- ERP Commercial Material ID
- ERP Commercial Material Name
- ERP ACC Material ID
- ERP ACC Material Name
- Ops Technical Material ID
- Material Type
- Status
- Date Created
- Material Description

Additional Information -

- When viewed in edit mode, only the current values of fields (based on effective date) will be displayed. If a recently updated value is older than the current value, it will be saved. However, these values will not be displayed in edit mode but can be viewed by downloading the Excel history.
- Only one value can exist for a given effective date. In Edit mode, if a record with the same effective date already exists in the system, the user will receive a warning and be asked if they want to proceed and overwrite the existing details.
- Historical and future data can be viewed by downloading the Excel file using the download option in View mode.
 - **Effective Date*:**
 - Editable and pre-populated with the existing value.
 - Default value - Current date

- Mandatory: Yes
 - **Unit Weight***
 - Editable and pre-populated with the existing value.
 - Default value - None
 - Mandatory: Yes
 - **Density**
 - Editable and pre-populated with the existing value.
 - Default value - None
 - Mandatory: No
- **Action Buttons**
 - **Save & Continue:**
 - Upon saving the details, the user is redirected to the **Material Specification** tab.
 - On the **list screen**:
 - An **Edit** option will appear in the **action menu** for the corresponding item.
 - Since Material Specification has default 0 values, User can now activate the material.
 - **Cancel:** Cancels the current operation and returns to the list screen

Material Specification Tab

- Users can edit material specifications, including chemistry, physical and size specifications.
- Under this section “Low”, “Aim” and “High” values for various elements are captured. The elements are mapped to a particular material type.
- In Edit mode update of element values inserts a new set of records with the date.
- For any given date only one set can exist, the older values will be overwritten for an existing date. Thus, storing historical data will help generate reports with appropriate data for all dates.

- Historical data can be viewed by downloading the Excel file using the download option in View mode
- The list of elements for Chemical and Physical can be seen in the design provided.
- **Each Chemistry element will have the following**
 - Low -
 - Editable and pre-populated with the existing value.
 - Default value - 0
 - Mandatory: No
 - Field Validation -
 - only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be lower than Aim and High
 - Aim
 - Editable and pre-populated with the existing value.
 - Default value - 0
 - Mandatory: No
 - Field Validation -
 - only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be higher than Low and lower than High
 - High
 - Editable and pre-populated with the existing value.
 - Default value - 0
 - Mandatory: No
 - Field Validation -
 - only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be higher than Low and Aim
- **Each Physical element will have the following**
 - Low -
 - Editable and pre-populated with the existing value.
 - Mandatory - No
 - Default - 0
 - Field Validation -
 - only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be lower than Aim and High
 - Aim
 - Editable and pre-populated with the existing value.
 - Mandatory - No
 - Default - 0
 - Field Validation -
 - only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be higher than Low and lower than High

- High
 - Editable and pre-populated with the existing value.
 - Mandatory - No
 - Default - 0
 - Field Validation -
 - only integers, Max 100/ Min 0, 3 integers and Four places after decimal point
 - It has to be higher than Low and Aim
- **Action Buttons**
 - **Save**
 - Upon saving the details, the user is redirected to the **List** page.
 - On the **list screen**:
 - Since both tab's details have been entered,
 - An **Edit** option will appear in the **action menu** for the corresponding item.
 - User can now activate the material
 - **Cancel**: Cancels the current operation and returns to the list screen

← C910_9 | SiO2DM

Nora James

Material Information | Material Specification

Chemistry Elements

Elements (in %)	Low	Aim	High
Al	0.0000	0.0000	0.0000
As	0.0000	0.0000	0.0000
Au	0.0000	0.0000	0.0000
B	0.0000	0.0000	0.0000
Be	0.0000	0.0000	0.0000
C	0.0000	0.0000	0.0000
Ca	0.0000	0.0000	0.0000
Cd	0.0000	0.0000	0.0000
Ce	0.0000	0.0000	0.0000
Co	0.0000	0.0000	0.0000
Hf	0.0000	0.0000	0.0000
Hg	0.0000	0.0000	0.0000
In	0.0000	0.0000	0.0000
K	0.0000	0.0000	0.0000
La	0.0000	0.0000	0.0000
Li	0.0000	0.0000	0.0000
Mg	0.0000	0.0000	0.0000
Mn	0.0000	0.0000	0.0000
Mo	0.0000	0.0000	0.0000
Na	0.0000	0.0000	0.0000
Sb	0.0000	0.0000	0.0000
Sc	0.0000	0.0000	0.0000
Se	0.0000	0.0000	0.0000
Si	0.0000	0.0000	0.0000
Sm	0.0000	0.0000	0.0000
Sn	0.0000	0.0000	0.0000
Sr	0.0000	0.0000	0.0000
S	0.0000	0.0000	0.0000
Ta	0.0000	0.0000	0.0000
Te	0.0000	0.0000	0.0000

Cancel Save

4. View Material

This screen will allow users to input and manage records, organised into two Tabs: Material Information and Material Specification. Mandatory fields will be marked with an asterisk (*). Below is a detailed layout incorporating the requirements.

Header: Back Icon | **D030_24 | Bec 0/25** ((Material ID | Material Name) | **Edit Icon:** Allows users to switch from view mode to edit mode to update the record.

Material ID	Material Name	Material Type	Created At	Status
C910_9	SIO2DM	Silica Fume	10/10/2024	Active
C910_7	SIO2MWDWM	Silica Fume	10/10/2024	Active
DSF1_204	PS Silicium brut 2.5 / 5	Silica Fume	10/10/2024	Active
C910_272	SIO2DP FIBRE CEMENT	Silica Fume	10/10/2024	Active
DSF1_161	PS SILICIUM 1.2 / 2.5	Silica Fume	10/10/2024	Active
C910_8	SIO2MR	Silica Fume	10/10/2024	Inactive
D046_279	HF Interne	Silica Fume	10/10/2024	Active
C910_271	SIO2DP PREMIUM	Silica Fume	10/10/2024	Active
C910_214	SIO2-DP	Silica Fume	10/10/2024	Inactive
C910_273	SIO2 DM PREMIUM	Silica Fume	10/10/2024	Active

Material Information Tab

Basic Information (Read-only; fetched from external ERP system):

- Material ID = (Concatenation of ERP ID and Ops ID)
- Material Name

- ERP Commercial Material ID
- ERP Commercial Material Name
- ERP ACC Material ID
- ERP ACC Material Name
- Ops Technical Material ID
- Material Type
- Status
- Date Created
- Material Description

Additional Information - These details are to be captured here, they are the following

- **Effective Date:**
 - **Export Icon:**
 - Historical and future data can be viewed by downloading the CSV file using the download option.
 - The tooltip should read “Download CSV”.
 - Downloads the record in CSV format.
 - The file must include the following headers and display the values as the following example:
 - Exported File Name: **“By Prodcuts_Additional_Information_DDMMYY**

Effective Date	Material ID	Material Name	Material Type	Unit Weight	Density	Created By	Modified By	Created At	Modified At
22/05/25	C910_8	SIO2MR	Silica Fume	12.00t	1.00 g/cm ³	superuser superuser Rose Danish	superuser superuser Rose Danish	22/05/2025 09:39 AM	22/05/2025 09:39 AM

- **Unit Weight**
- **Density**

</

Material Specification Tab

Chemistry, Physical of various elements will be available in read only mode.

Each Chemistry element will have the following

- Low
- Aim
- High

Each Physical element will have the following

- Low
- Aim
- High

Export Specification

- Historical data can be viewed by downloading the Excel file using the download option.
- The tooltip should read “Download CSV”.
- Downloads the record in CSV format.
- The file must include the following headers and display the values as the following example:
- Exported File Name: “**By Prodcuts_MaterialSpecification_DDMMYY**”

Element (in %)	Element Group	Low	AIM	High	Plant Material ID	Plant	Created At	Created By	Modified At	Modified By
-------------------	------------------	-----	-----	------	-------------------------	-------	------------	------------	-------------	-------------

Al	CHE	0	0	708	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
As	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Au	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Be	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
B	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Ca	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Cd	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Ce	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Co	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Cr	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Cu	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
C	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Dy	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Er	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Fe	CHE	0	0	08	6V_C 910_ 8	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish

Ga	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Gd	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Ge	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Hf	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Hg	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
In	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
K	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
La	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Li	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Mg	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Mn	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Mo	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Na	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Nb	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Nd	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish

Ni	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Pb	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Pr	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Pt	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
P	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Re	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Sb	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Sc	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Se	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Si	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Sm	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Sn	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Sr	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
S	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Ta	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish

Te	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Ti	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
V	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
W	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Y	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Zn	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Zr	CHE	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Ash	PHY	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Moistur e	PHY	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish
Volatile s	PHY	0	0	08	6V_C 910_ 6V	02/06/2025 07:52 AM	superuser Rose Danish	02/06/2025 07:52 AM	superuser Rose Danish

←

C910_9 | SIO2DM

✎

Material Information

Material Specification

View Change History

Chemistry Elements

Elements (in %)	Low	Aim	High
Al	0.0000	0.0000	0.0000
As	0.0000	0.0000	0.0000
Au	0.0000	0.0000	0.0000
Be	0.0000	0.0000	0.0000
B	0.0000	0.0000	0.0000
Ca	0.0000	0.0000	0.0000
Cd	0.0000	0.0000	0.0000
Ce	0.0000	0.0000	0.0000
Co	0.0000	0.0000	0.0000
Cu	0.0000	0.0000	0.0000

Elements (in %)	Low	Aim	High
Hf	0.0000	0.0000	0.0000
Hg	0.0000	0.0000	0.0000
In	0.0000	0.0000	0.0000
K	0.0000	0.0000	0.0000
La	0.0000	0.0000	0.0000
Li	0.0000	0.0000	0.0000
Mg	0.0000	0.0000	0.0000
Mn	0.0000	0.0000	0.0000
Mo	0.0000	0.0000	0.0000
Nb	0.0000	0.0000	0.0000

Elements (in %)	Low	Aim	High
Sb	0.0000	0.0000	0.0000
Sc	0.0000	0.0000	0.0000
Se	0.0000	0.0000	0.0000
Si	0.0000	0.0000	0.0000
Sm	0.0000	0.0000	0.0000
Sn	0.0000	0.0000	0.0000
Sr	0.0000	0.0000	0.0000
S	0.0000	0.0000	0.0000
Ta	0.0000	0.0000	0.0000
Ti	0.0000	0.0000	0.0000

View Change History

This button opens a modal or section showing a chronological list of all changes made to the record, including:

- Timestamp of change
- Field(s) modified
- Previous and updated values
- Name of the user who made the change
- **Export Icon - Downloads the records in CSV format, the tooltip should read “Download CSV”.**
- Export Filename - “By Prodcuts_ChangeHistory_DDMMYY”

Specification Change History			Old			New		
Date	Username	Element	Low	Aim	High	Low	Aim	High
05/01/2025 09:00 AM	JSmithOperator	Al	0.0000	0.0000	0.0000	1.9000	2.0000	2.4500
04/01/2025 09:00 AM	superadmin	Ca	0.0000	0.0000	0.0000	0.0000	1.0000	0.0000
		Al	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
02/01/2025 07:00 AM	superadmin	Coarse Particles (>45um)	0.0000	0.0000	0.0000	0.0000	0.0000	2.4500
01/01/2025 09:00 AM	superadmin	Cl	0.0000	0.0000	0.0000	0.0000	1.0000	0.0000